



Bringing Big Business Solutions to Everyday People

How to Download TrackemPlus from Motorola

To download TrackemPlus:

1. Press the 'Menu' button on the phone.
2. Scroll down and select 'Java Apps'. On the next screen, scroll down and select 'Download Apps'.
3. From the download screen, scroll down and select 'Free/Demo'.
4. You will see 'TrackemPlus' as an option. Scroll down and select 'TrackemPlus'.
5. You will get a screen with the application details, which lists the following: "Name: TrackemPlus, Data Size for Download: 53KB, Program Size: 72KB"
6. Click 'Get It' to download the application. Once downloaded, a 'Thank You' screen will appear.

TrackemPlus is now downloaded onto your handset. Install TrackemPlus following the normal procedures for Java applications (instructions below).

To install TrackemPlus:

7. Go back to the main menu on your phone, and go to 'Java Apps'.
8. Select 'TrackemPlus' from the list that shows up, and select 'Install'. (Note: The handset may go through an initialization phase. If so, and prompted, select 'Next'.
9. You will be prompted again with 'Add suite/MIDlet to main menu?' Select 'No'.

To setup TrackemPlus:

10. Launch the TrackemPlus application.
11. Click the Menu button on your handset, to bring up TrackemPlus's menu, and go to 'Set-up'.
12. Enter your phone number and User PIN. The User PIN is the last 4 digits of your phone number. Click 'Save'.
13. Go back to the main menu on your phone. Launch the browser to check data connectivity. Once the browser successfully launches a page, close your browser. If it can not connect, contact Telus Channel Care to check on your data plan, or reset your browser.
14. Go back to the main menu on your phone. Go to, GPS > Privacy, and set the option to 'Unrestricted'.
15. Go back to the main menu on your phone. Go to, Settings > Personalize > Power Up. Change 'App Default' to 'TrackemPlus'.
16. Leave TrackemPlus running, and place the handset either in a car, or near a window. The first GPS hit can take up to 30 minutes to register.